

Firmware Release Note

HT100 HACCP Touch



Date: 15th September 2016

Version: B2.47/B2.48

Fixes:

Improved checking of thermocouple Burn Out detection.

Enhancements: None

Firmware Release Note

HT100 HACCP Touch



Date: 19th May 2016

Version: B2.42/B2.46

Fixes:

T50: Fixed

T51: Fixed problem of Cleaning checks not showing more than 5

Fixed problem of time reverting to 24hr mode after restart.

Fixed problem of reading time format from config file

Now adds time and date format to LOGFILE.TXT. Removed from LOGFILE.XML

Enhancements: None

Firmware Release Note

HT100 HACCP Touch



Date: 15th Feb 2016

Version: 2.41

Fixes:

T31: Fixed problem of Equipment Checks not scrolling past 5 checks

T32: Fixed problem of Corrective Actions not being offered for General Checks

T38: Fixed problem of Record button not changing colour in 3 temp models

T40: Fixed problem of when recheck function is enabled and to be selected, the Record button does not change the colour and if record button selected again, the change colour function can be re-activated

T41: Fixed problem of in 3 sample check function, triangle cannot clear after set

E3: Related to **T32**

E4: Related to **T31**

E5: Fixed problem of Yellow Triangles coming up on Re-Heat for failed temperatures but not on any other part of the program

Enhancements: None

Firmware Release Note

HT100 HACCP Touch



Date: 09th Oct 2015

Version: 2.24

Fixes:

T31: Fixed problem of Equipment Checks not scrolling past 5 checks

Enhancements: None

Firmware Release Note

HT100 HACCP Touch



Date: 26th June 2015

Version: 2.24

Fixes:

T29: After a valid temperature check the handheld now returns to the product list. Previously it was returning to the location list.

T30: Fixed the problem of when traversing back through the menus' the location and product lists were corrupted when greater than 5 items present.

Enhancements: None

Firmware Release Note

HT100 HACCP Touch



Date: 22nd May 2015

Version: 2.23

Fixes:

T22: Fixed problem of Warning triangles not being shown correctly after an out of range check

T23: Receiving summary page now only shows Delivery Code if set up to request it

T27: Warning triangle now clears if temperature passes check (previously did not clear)

T28: If nothing setup under cooking, now shows a warning pop-up (previously unit restarted)

Enhancements: None

Firmware Release Note

HT100 HACCP Touch



Date: 26th March 2015

Version: 2.21

Fixes:

T21: Fixed a problem where pressing BACK does not take you to the previous screen on Food Checks.

Enhancements: None

Firmware Release Note

HT100 HACCP Touch



Date: 17th March 2015

Version: 2.20

Fixes:

T17: Improved handling of error conditions when checks are not present in the database. Now shows a pop up instead of defaulting to a generic error screen.

T18: Fixed problem of receiving checks not following the requirements specified in the PC Software. Back and Next buttons now navigate properly through receiving. Improved handling of temperatures within the code to remove scaling. Fixed problem of exactly -20.0 C showing "Error"

T19: Fixed problem on Equipment checks where if no bounds were set up for a check a corrective action was asked for. Fixed Back button functionality on Equipment temperature check page.

T20: Fixed a problem on Equipment checks where Finish being pressed after a recheck did not take a new reading. Improved response of the Finish button on the Equipment checks page which required a number of presses before activating.

Enhancements: None

Firmware Release Note

HT100 HACCP Touch



Date: 18th February 2015

Version: 2.14 & 2.13

Fixes:

T15: Added a Pop up if no checks are in the database for food temperature checks.

Enhancements: None

Notes:

2.14 is the same as 2.13 but the backlight timeout set to 30 minutes to help demonstrations.

Firmware Release Note

HT100 HACCP Touch



Date: 2nd December 2014

Version: 2.12 & 2.11

Fixes:

T15: Added a Pop up if no checks are in the database for food temperature checks.

Enhancements: None

Notes:

2.12 is the same as 2.11 but the backlight timeout set to 30 minutes to help demonstrations (**T13**)

Firmware Release Note

HT100 HACCP Touch



Date: 26th November 2014

Version: 2.10

Fixes:

T5: When performing a recheck the previous selected corrective action is now cleared.

T7: Fixed problem where continuous re-check caused the handheld to crash.

Fixed problem where pressing back on the recheck screen caused a green tick to appear on the corrective actions list when nothing had been entered.

T11: Fixed Problem of corrupted contents in the location column on the log file for export.

Enhancements:

T4: Screen off time increased to 1 Minute

T6: User must now select 1 corrective action before moving away from the screen.

T8: Removed cooling

T10: Changed order of main screen to "Food Temp", "Equipment Checks", "Receiving", "General Checks"

Firmware Release Note

HT100 HACCP Touch



Date: 10th November 2014

Version: 2.08

Fixes:

T5: When performing a recheck the previous selected corrective action is now cleared.

T7: Fixed problem where continuous re-check caused the handheld to crash. Fixed problem where pressing back on the recheck screen caused a green tick to appear on the corrective actions list when nothing had been entered.

T11: Fixed Problem of corrupted contents in the location column on the log file for export.

Enhancements:

T4: Screen off time increased to 1 Minute

T6: User must now select 1 corrective action before moving away from the screen.

T8: Removed cooling

T10: Changed order of main screen to "Food Temp", "Equipment Checks", "Receiving", "General Checks"