

## RF300 – New Cloud Upgrades for Sept 2017

Issue 1 – 20/09/2017

Comark is pleased to announce some significant upgrades to the Comark Cloud for RF300 Loggers.

Several new features have been added to improve usability and Alarm Alerting. Please see below....

### Comment to Event Log for Alarm Acknowledge

When an alarm is now acknowledged by the user, via the web page, a comment is now added to the event log stating which user was signed in.

### Audit Events recorded

Added no of Audit events to summary report and page view

### Alarm Readings Added to Data Tab

Add alarm readings to Data tab view

### Audit Events Added to Data Tab

Add Audit Events to Data tab view

### Alarm Readings added to Data Exports

Add alarm readings data export documents

### Audit Events added to Data Export

Add Audit Events to data export documents

### Test E-mail

Test email facility to confirm e-mails to recipients will be sent/received. See Test E-mail button next to each e-mail recipient setup for the Logger.

### Repeat E-mails

Resend emails until event is cleared. Repeat alarms can be sent after 15, 30, 45 or 60 minutes. Repeat E-mails are setup on a per logger basis.

### Escalate Alarm E-mails

Escalate alerts to another e-mail address if event is not cleared. Escalation e-mails can be sent after 5, 10, 15, 30, 45 or 60 minutes. Escalation E-mails are setup on a per logger basis.

End.

Comark Instruments  
52 Hurricane Way, Norwich, Norfolk, NR6 6JB, UK  
Tel: +44 207 942 0712  
www.comarkinstruments.com

Comark Instruments  
PO Box 500, Beaverton, OR 97077, USA  
Tel (503) 643 5204  
www.comarkUSA.com